

LookSky – Quick start

Contents:

1. General information	2
2. Quick start	2
2.1. Initial user settings	2
2.2. Series loading	2
2.3. Visual analysis of the moving objects	5
2.4. Hand measuring of the not detected objects	8
2.5. Saving the results of work	10
2.6. Reports sending	10

1. General information

LookSky – is a new cross-platform version of the frames viewer of the **CoLiTec** software for automated asteroids and comets discoveries in a series of CCD-frames.

The main features of **LookSky** for the quick start are the following:

- visual analysis of the moving objects (asteroids, comets) detected in automation mode by **CoLiTec** software;
- deleting the false objects (it is necessary to pay attention to the previously unknown objects);
- hand measuring of the objects (asteroids, comets) that were not detected in automation mode;
- saving the results of work;
- creation and sending the reports.

2. Quick start

After the successful processing of a series of frames by **CoLiTec** software perform quick start of **LookSky**. To do this, launch the executable file accordingly to the operating system: «**LookSky.exe**» (Windows) or «**LookSky**» (Linux).

2.1. Initial user settings

During the first launching of **LookSky** (figure 1) perform the initial user settings. For this open **LookSky** settings by menu «*File → Profile LookSky*».

The following settings are available: localization settings, saving of the parameters and windows position, automated objects searching and loading from the active series.

2.2. Series loading

After initial user settings load the series of frames processed by **CoLiTec** software using menu «*File → Open zones...*». In the appeared dialog window find and select the folder with the processed series of frames. The loading process may take several seconds.




Figure 1. LookSky during the first launching

After loading the series of frames the activation window will appear (figure 2).




Figure 2. Activation window

Select «Yes» button for the frame activation from loaded series. After this the frame will appear in the «Image view» window (figure 3).




Figure 3. Image view window

You can set position and size of all windows in the program according to the used monitor to increase usability (figure 4).




Figure 4. Windows location after series loading

Also set the mode for the frames centering by stars for the convenient blinking of frames in series (figure 5).




Figure 5. Setting the mode for the frames centering by stars

For the visual analysis of the moving objects (asteroids, comets) detected in automation mode by CoLiTec software, «Manager Objects» window should be opened (figure 6).




Figure 6. Manager objects window

After successful series loading and activation the list of detected moving objects (asteroids, comets) will appear in «Manager Objects» window.

2.3. Visual analysis of the moving objects

Blinking mode should be started for the visual analysis of the moving objects detected in automation mode by CoLiTec software (figure 7).




Figure 7. Blinking mode for visual analysis of the detected moving objects

During the frames blinking analyze all objects from «Asteroids - Data of CoLiTec» list. For this, select every object in «Manager Objects» window using mouse or cursors control buttons and analyze object's image in the «Image view» window.

Next, make a decision – is this object real or it is the false detection? Uncheck appropriate checkboxes in the «Draw» column for all false objects to prevent including them to the report.

Use the frame navigation modes for a quick navigation to the moving objects (asteroids/comets) detected on a series of frames. (figure 8).




Figure 8. Frame navigation modes

LookSky allows selection of parameters of the detected objects to display.

For selection of necessary parameters to display perform RMB click on the area with headers of data in the window with «Asteroids - Data of CoLiTec» list, as shown on the figure 8.1.




Figure 8.1. Selection of parameters of the detected objects to display

In the appeared window (figure 8.2) select and set necessary parameters to display.




Figure 8.2. The window for selecting and setting the displayed parameters

2.4. Hand measuring of the not detected objects

For the quality control of the automated moving objects detection by **CoLiTec** software you can also use the data from the Minor Planet Center (MPC) catalog.

This information is available in «*Asteroids of Minor Planet Center*» list of «*Manager Objects*» window (figure 9). It contains the data about known asteroids/comets that were verified.

Verify that all available asteroids/comets from this list were detected by **CoLiTec** software.

If the object has two selection: red (MPC) and yellow (CoLiTec), it is the known asteroid or comet and was successfully detected and measured by **CoLiTec** software.




Figure 9. Data from the Minor Planet Center (MPC) catalog

In case if some objects (asteroids/comets) were not detected by **CoLiTec** software and there is only one red (MPC) selection of these objects you should perform the hand measuring of all not detected objects.

Use «*Tools → Hand Measurer*» menu for this (figure 10).




Figure 10. Hand measurer opening

The measuring of the object's image in the current frame can be performed by clicking on Ctrl+LMB. Perfrom measuring of this object for all frames of series. Then press «*Make object*» button and this new object will be added to «*Asteroids - Data of CoLiTec*» list (figure 11).




Figure 11. Hand measuring of the not detected object

2.5. Saving the results of work

Save the results of work after analysis of all moving objects (asteroid / not asteroid), known objects from the Minor Planet Center (MPC) catalog in «*Manager Objects*» window and hand measuring of all not detected objects, i. e. current status of all checked and unchecked objects from «*Asteroids - Data of CoLiTec*» and «*Asteroids of Minor Planet Center*» lists (figure 12).




Figure 12. Saving the results of work

2.6. Reports sending

Create report after saving the results of work (figure 13).




Figure 13. Report window opening

IMPORTANT! To send reports from **LookSky** set E-mail settings in «*User settings* → *E-mail* → *Sender*» section and check fields in «*MPC recipient*» section in the settings editor **ThresHolds**. Report also can be saved as text file and sent manually from the preferred mail service.

If several series were downloaded, **LookSky** provides the opportunity to generate a consolidated report for several series (figure 14).




Figure 14. Report creation for sending